

# FOXIT PDF READER DEPLOYMENT AND CONFIGURATION

**For Windows** 

© Foxit Software Incorporated. All Rights Reserved.

No part of this document can be reproduced, transferred, distributed or stored in any format without the prior written permission of Foxit.

Anti-Grain Geometry – Version 2.3

Copyright (C) 2002-2005 Maxim Shemanarev (<a href="http://www.antigrain.com">http://www.antigrain.com</a>)

Permission to copy, use, modify, sell and distribute this software is granted provided this copyright notice appears in all copies. This software is provided "as is" without express or implied warranty, and with no claim as to its suitability for any purpose.

# **Contents**

Introduction About the User Manual	. 1
	. 1
ADOUL LITE USET INIATIONAL	
About Foxit PDF Reader (MSI)	
Foxit PDF Reader (MSI) Overview	. 1
Installing Foxit PDF Reader	
Deployment and Configuration	
Using Group Policy	
What is Group Policy?	
Personal Computer Setting	
GPO Deployment (for Server)	
GPO Items1	
Using Foxit Customization Wizard1	19
Get started1	
Contact Us2	

# Introduction

#### **About the User Manual**

Foxit PDF Reader (MSI) is developed on the basis of Foxit PDF Reader (EXE), but it extends the usability and performance of viewing and editing of Foxit PDF Reader (EXE). This User Manual introduces the deployment and configuration of Foxit PDF Reader. Please follow the instructions below for details.

### **About Foxit PDF Reader (MSI)**

#### Foxit PDF Reader (MSI) Overview

Foxit PDF Reader (MSI), hereafter referred to as Foxit PDF Reader, is a PDF document viewer. It launches quickly and is easy to install. Just run "Foxit PDF Reader Setup.msi" and then follow the <u>installation guides</u> to complete installation.

Foxit PDF Reader enables users to edit and secure reliable PDF documents quickly, easily and economically. In addition to the basic PDF viewing functions, Foxit PDF Reader also includes various advanced features, such as AIP Protection, GPO Control, and XML Control.

#### **Installing Foxit PDF Reader**

#### **Windows System Requirements**

Foxit PDF Reader runs successfully on the following systems. If your computer does not meet these requirements, you may not be able to use Foxit PDF Reader.

#### **Operating Systems**

- Windows 10
- Windows 11
- Verified as Citrix Ready® with Citrix XenApp® 7.13

#### **Recommended Minimum Hardware for Better Performance**

1.3 GHz or faster processor (x86 compatible) or ARM processor, Microsoft SQ1 or

better

- 512 MB RAM (Recommended: 1 GB RAM or greater)
- 1 GB of available hard drive space
- 1024\*768 screen resolution
- Supports 4K and other high-resolution displays

#### How to Install?

- Double-click the installation file and you will see the Install Wizard pop up. Click Next to continue
- In order to install Foxit PDF Reader on your system, you are required to accept the terms and conditions of Foxit's License Agreement. Please read the Agreement carefully and then check I accept the terms in the License Agreement to continue. If you cannot accept it, please click Cancel to exit the installation.

(Optional) You can select or deselect the **Help improve user experience** option to turn on or off data collection. The collected data will be used to improve user experiences only. The setting for this option will not affect the following installation process.

- Choose one of the setup types as needed:
  - A. **Typical** –installs all features by default but requires more disk space.
  - B. **Custom**—allows users to choose the features to be installed.
- For Typical setup, just click Install. For Custom setup, do the following:
  - A) Click **Browse** to change the installation directory of the PDF Viewer plug-in.
  - B) Click **Disk Usage** to check the disk space available for the selected features.
  - C) Check the options you want to install and click **Next** to continue.
  - D) Select the additional tasks you would like to perform while installing Foxit PDF Reader, click **Next** and then **Install** to begin the installation.
- Finally, a message will appear to inform you the successful installation. Click **Finish** to complete the installation.

#### **Command-line Installation**

You can also use the command-line to install the application:

msiexec /Option <Required Parameter> [Optional Parameter] [PROPERTY=PropertyValue]

For detailed information on msiexec.exe options, required parameters, and optional

parameters, type "msiexec" on the command line or visit Microsoft TechNet help center.

#### Public Properties of the Foxit PDF Reader MSI installation package.

Foxit PDF Reader installation properties supplement the standard MSI public properties to give administrators greater control over the installation of the application.

For the complete list of standard public properties please refer to: <a href="http://msdn.microsoft.com/en-gb/library/aa370905(VS.85).aspx">http://msdn.microsoft.com/en-gb/library/aa370905(VS.85).aspx</a>

The Foxit PDF Reader properties are:

\_\_\_\_\_\_

**ADDLOCAL** < list of features>The value of the ADDLOCAL property is a comma

delimited list of features which the installation of Foxit PDF Reader will make available locally. Foxit PDF Reader

installer defines the following features:

**FX\_PDFVIEWER** - Foxit PDF Viewer and its components;

**FX\_FIREFOXPLUGIN** – A plugin used for opening PDF files in Internet Explorer. This feature requires FX\_PDFVIEWER

feature to be installed.

**FX\_SPELLCHECK** - Spell check tool which is used for finding any misspelled words in typewriter or form filler mode and suggesting the correct spellings. This feature requires

FX\_PDFVIEWER feature to be installed.

**FX\_SE** - Plugins for Windows Explorer and Windows shell. These extensions allow PDF thumbnails to be viewed in Windows Explorer, and PDF files to be previewed in Windows OS and Office 2013 (or a later version). This feature requires FX\_PDFVIEWER feature to be installed.

**INSTALLLOCATION** Specifies the folder where products will be installed.

MAKEDEFAULT Default value of "1", Foxit PDF Reader will be set as default

application for opening PDF files.

**VIEW\_IN\_BROWSER** Default value of "1", Foxit PDF Reader will be configured to

open PDF files inside browsers.

**DESKTOP\_SHORTCUT** Default value of "1", installer will place a shortcut for the

installed application on Desktop.

STARTMENU\_SHORTCUT Default value of "1", installer will create program menu

group for installed application and its components.

**LAUNCHCHECKDEFAULT** Default value of "1", Foxit PDF Reader will check if it is the

default reader when it's launched.

**CLEAN** Executes with the command /uninstall, removing all of

Foxit PDF Reader's registry data and related files with the value of "1". (Note: This is a command for uninstallation.)

**AUTO\_UPDATE** Do not download or install updates automatically with the

value of "0"; Automatically download updates, but let users choose when to install them with the value of "1";

Automatically install updates with the value of "2".

**REMOVENEWVERSION** Forces an installation to overwrite the higher version of

Foxit PDF Reader with the value of "1".

**REMOVEGAREADER** Forces to uninstall Foxit PDF Reader (Desktop Version).

**NOTINSTALLUPDATE** Does not install updates by setting the value to "1". This

will prevent Foxit PDF Reader from being updated from

within the software.

**INTERNET\_DISABLE** Disables all features that require an Internet connection by

setting the value to "1".

**READ\_MODE** Opens PDF file in Read Mode by default in web browsers

by setting the value to "1".

**DISABLE\_UNINSTALL\_SURVEY** Stops the Uninstall Survey after uninstallation by setting

the value to "1".

**KEYCODE** Activates the application by key code.

**EMBEDDED PDF INOFFICE** With the value of "1", opens embedded PDF files in

Microsoft Office with Foxit PDF Reader if Acrobat and

Foxit PDF Editor is not installed.

**ADVERTISE** Usually used together with "ADDLOCAL" to advertise the

specified features.

Command-line Examples:

1. Silently install the application (no user interaction) to folder "C:\Program Files\Foxit

Software":

msiexec /i "Foxit PDF Reader.msi" /quiet INSTALLLOCATION="C:\Program Files\ Foxit Software "

2. Install Foxit PDF Viewer only:

msiexec /i "Foxit PDF Reader.msi" /quiet ADDLOCAL="FX\_PDFVIEWER"

3. Force an installation to overwrite the same or higher version of Foxit PDF Reader:

msiexec /i "Foxit PDF Reader.msi" REMOVENEWVERSION="1"

4. Remove registry and user data when performing silent uninstallation:

msiexec /x "Foxit PDF Reader.msi" /quiet CLEAN="1"

5. Activate the application by key code:

msiexec /i "Foxit PDF Reader.msi" KEYCODE="your key code"

# **Deployment and Configuration**

# **Using Group Policy**

#### What is Group Policy?

Group Policy (GPO), a feature of the Microsoft <u>Windows NT</u> family of <u>operating systems</u>, is a set of rules that control the working environment of user accounts and computer accounts. It offers the centralized management and configuration of operating systems, applications, and users' settings in an <u>Active Directory</u> environment.

Group Policy can configure most system settings, save power by utilizing smart power settings, give individual users more control over their machines with administrator privileges and increase system security.

Group Policy in part controls what users can and cannot do on a certain program to accomplish the goal of central management of a group of applications. Users can configure Foxit PDF Reader easily through Group Policy. Please refer to the instructions below for details.


#### **Personal Computer Setting**

Foxit PDF Reader offers two types of group policy template: .adm and .admx. Different types are compatible with different operation systems, but have the same settings. The template of .adm file type is compatible with Windows XP and later, while .admx is compatible with Server 2008, Server 2012, Windows 10 and later.

#### **Set Template Preference**

For .adm file, follow the steps as below:

- Please click Start > Run or use the shortcut key Windows + R and type gpedit.msc to open Local Group Policy Editor.
- Right-click the management template and choose Add/Remove Templates in the
  context menu. In the opened dialogue box, add the group policy template of Foxit
  PDF Reader (Foxit PDF Reader.adm). The Foxit PDF Reader template will appear in
  the left navigation pane and you can set its template preferences.




For .admx file, put the .admx file in C:\Windows\PolicyDefinitions and do the setting. The .admx file should be used in combination with an .adml file. And the .adml file should be put in C:\Windows\PolicyDefinitions\language. For example, if in the English OS, the .adml file should be put in C:\Windows\PolicyDefinitions\en\_us.

See **Set Plugins** as an example for other options are configured in the same fashion.

- Choose Foxit PDF Reader 12.0 > Plugins.
- Double-click **Remove Plugins** to open the dialog box.
  - Select Enabled, check the submenus to be removed in the Options, and click OK or Apply. The corresponding submenu items will then be removed from Foxit PDF Reader.

**Note**: If you select all the submenus in the **Options** and confirm the configuration, all of the submenus will be removed.

If you select **Disabled** or **Not Configured**, no changes will be applied to Foxit PDF Reader.




**Note**: Group Policy setting includes computer configuration and user configuration. Computer configuration takes precedence over user configuration. The application will use the computer configuration if both the computer and user configure a specific function at the same time. Please note that if the option **Disabled** is a valid configuration, the setting will be shown in the help information. Otherwise, the corresponding registry entry will be removed as selecting Unconfigured. (The value of the option Disabled in the Group Policy Template of Foxit PDF Reader is invalid.) Foxit PDF Reader will retain all your configuration settings when you upgrade it to a new version.


#### **GPO Deployment (for Server)**

#### **Create GPO Management**


- If you already have an Active Directory domain and organizational unit configured, please skip to "Apply the Foxit Template" section.
- Choose **Start** > **Windows Administration Tools** > open "Active Directory Users and Computers" > right-click your domain > choose **New** > **Organization Unit**.




• In the opened **New Object-Organization Unit** dialogue box, type the unit name (For this example, we have named the unit "Foxit") and click **OK**.




Right click the created organization unit "Foxit" and choose New > User.
 For this example, we have named the user "tester01".






Click Start > Windows Administrative Tools > open the Group Policy Management
Console and right-click the created organization unit "Foxit" and choose Create a
GPO in this domain, and Link it here...




If you cannot find the Group Policy Management in Administration Tools, please install the application package GPMC.MSI. You can download the package by clicking the link <a href="http://www.microsoft.com/en-us/download/details.aspx?id=21895">http://www.microsoft.com/en-us/download/details.aspx?id=21895</a>.

**Note**: To deploy Foxit PDF Reader's installers or plugins through GPO, please refer to the instructions <u>here</u>. You can also perform the deployment through <u>Microsoft Intune</u> or <u>Configuration Manager</u>. Configuration Manager was previously named System Center Configuration Manager (SCCM) and now is part of Microsoft Endpoint Manager.


#### **Apply the Foxit Template**




• Type the GPO name in the **New GPO** dialogue box and click **OK**.



• Right-click the new GPO and choose **Edit** in the right-click menu to open Group Policy Editor.



 Right-click the **Template Management** and choose **Add/Remove Templates** to add Foxit PDF Reader template. Please refer to <u>Set Template Preference</u>.



• For configuring options, please refer to Example: Set Plugins.

#### **GPO Items**

The following table shows the deployable options and their functions in GPO to speed up your working process.

# **Items in GPO Template**

Folder Path	Item	Description
Foxit PDF Reader >	Tab Elements (the	Choose "Enabled" to configure the
Ribbon	items on Title Bar such	features in Ribbon.
	as the Quick Access	
	Toolbar and search	Choose "Hide this feature" to hide this
	field)	feature in Ribbon.
	Ribbon Category (the	
	command items in	Choose "Add to Quick Access Toolbar"
	each tab on the	to add this feature to Quick Access
	ribbon)	Toolbar.
Foxit PDF Reader >	Configure SharePoint	Configure a server URL for SharePoint.
Plugins	server URL	The changes will be synchronized to the
		corresponding settings under <b>File</b> >
		Open or Save As > Add a place >
		SharePoint.
	Configure Alfresco	Configure a server URL for Alfresco.
	server URL	The changes will be synchronized to the
		corresponding settings under <b>File</b> >
		Open or Save As > Add a place >
		Alfresco.
	Remove Specific	Input the plugin name which needs
	Plugins	to be removed.
		Only applications with .fpi extensions
		can be removed from Foxit PDF Reader.
	Remove Plugins	Remove selected plugins.
Foxit PDF Reader >	Itself	Specify whether to enable all the
Preferences >		features which require an Internet
Features which		connection. This will change the
require internet		corresponding setting in <b>Preferences</b> >
connection	6 11	General.
	SubItem	Specify the features that allow Internet
		connection. The specified features will
		be allowed to access the Internet even
		though you have disabled all features
Favit DDF Dandars	Default DDC Vienner	which require an Internet connection.
Foxit PDF Reader >	Default PDF Viewer	Set Foxit PDF Reader as the default PDF
Preferences > File		viewer for 'System PDF Viewer' and

Association		'Web Browser PDF Viewer'.
	Disable default DDF	
Foxit PDF Reader >	Disable default PDF	Enable this option to disable the ability
Preferences > File	viewer switching	to change the specified default handler
Association		(PDF viewer).
Foxit PDF Reader >	Forbid Checking of	Hide the 'Set to Default PDF Reader'
Preferences > File	Default PDF Viewer	dialog when Foxit PDF Reader isn't the
Association		default PDF viewer.
Foxit PDF Reader >	All file attachments	Specify the default permission settings
Preferences >	may be opened or	of opening/saving non-PDF file
Security Settings	saved to disk	attachments.
Foxit PDF Reader >	Disable all actions in	Enable this option to disable all actions
Preferences >	PDFs	in PDFs.
Security Settings		
Foxit PDF Reader >	Disable Security	Enable this option to disable the
Preferences >	Warning	security warning when Foxit PDF
Security Settings		Reader is launched by a third-party
		application without a valid digital
		signature.
Foxit PDF Reader >	Edit the default list of	Set a whitelist and blacklist of file types
Preferences >	file types (Extension)	other than PDF to control which file
Security Settings	The types (Extension)	types of attachments are allowed to be
Security Settings		
Favit DDF Dandar	Undator	opened from a document.
Foxit PDF Reader >	Updater	Specify how to install the update when
Preferences > Update		a new version is available. This will lock
Settings		end users' ability to change the settings
		in Preferences > Updater >
		Automatically Update.
Foxit PDF Reader >	Add to Privileged	Enable this option to configure the
Preferences >	Locations	privileged locations, and lock end users'
Privileged Locations		ability to change the settings in
		Preferences > Security > Privileged
		Locations.
Foxit PDF Reader >	Lock Privileged	Enable this option to lock the end
Preferences >	Locations	user's ability to add files, folders, and
Privileged Locations		hosts as a privileged location to prevent
		them from continuing to assign trust.
		This will change the corresponding
		setting in <b>Preferences</b> > <b>Security</b> >
		Privileged Locations.
Foxit PDF Reader >	'About Foxit Reader'	Set the new contents in 'About Foxit
Preferences	Dialog	PDF Reader' dialog.
Foxit PDF Reader >	Advertisement	Change the settings of advertisement in
Preferences		right corner of the tab bar.
	i e e e e e e e e e e e e e e e e e e e	1

	T	
Foxit PDF Reader > Preferences	Application Language	Change the application language settings. This will change the setting
references		item in <b>Preferences</b> > <b>Languages</b> .
Foxit PDF Reader >	Change high DPI	Enable this option to change the high
Preferences	settings	DPI settings for Foxit PDF Reader.
Foxit PDF Reader >	Change The Link For	Enable this option to change the link of
Preferences	User Manual	User Manual to the local link you want.
Foxit PDF Reader >	Disable editing	Enable this option to disable and lock
Preferences	Manage Sites	the end user's ability to specify the
		default behavior for accessing the
		Internet from PDFs.
Foxit PDF Reader >	Do not allow new	Enable this option to not allow new
Preferences	account creation	account creation.
		The 'Create a new account' will not be
		displayed in the user login interface.
Foxit PDF Reader >	Do not use QuickTime	Enable this option to disable using
Preferences	Player for multimedia	QuickTime Player for multimedia items.
	items	
Foxit PDF Reader >	Enable creating	Disable this option to forbid the
Preferences	self-signed digital IDs	end-user to select "Create a new Digital
		ID" option in "Add ID" workflows.
Foxit PDF Reader >	Enable Safe Reading	Change the settings of Safe Reading
Preferences	Mode	Mode.
Foxit PDF Reader >	Filter Comments by	Enable this option to filter comments
Preferences	the original author	made by the original author only.
	only	Disable this option to filter
		comments made by all participants.
		This will change the corresponding
		setting in <b>Comment</b> > <b>Filter</b> window.
Foxit PDF Reader >	Hide the unnecessary	Enable this option to hide some login
Preferences	login methods in the	methods in user interface.
	login page	The selected login methods will be
5 11 DD 5 D		hidden in the user login interface.
Foxit PDF Reader >	JavaScript Action	Specify whether to allow the running of
Preferences		JavaScript in PDF files. This will change
		the corresponding setting in
		Preferences > JavaScript > Enable
E DDE D	Landen to L	JavaScript Actions.
Foxit PDF Reader >	Load trusted	Specify whether to load the trusted
Preferences	certificates from Foxit	certificates from Foxit server
	server	automatically, and how to update the
		trusted certificates. This will change the
i		corresponding setting in <b>Preferences</b> >

		Trust Manager > Automatic Foxit
		Approved Trust List updates.
Foxit PDF Reader > Preferences	Lock Read Mode in web browsers	Change the Read Mode setting in web browsers. This will change the corresponding setting in <b>Preferences</b> > <b>Documents</b> > <b>Open Settings</b> .
Foxit PDF Reader >	Lock the	Enable this option to lock the
Preferences	Auto-Complete in Form Filling	Auto-Complete feature and disable the corresponding setting in <b>Preferences</b> > <b>Forms</b> .
Foxit PDF Reader > Preferences	Multiple Windows	Enable this option to always open files in a new window. Disable this option to not open files in a new window. This will change the corresponding setting in <b>Preferences</b> > <b>Documents</b> .
Foxit PDF Reader > Preferences	Notification Messages	Enable this option and choose how to deal with the different notification messages. If you unchecked all the options, the notification messages will never be shown. This will change the corresponding setting in <b>Preferences</b> > <b>General</b> .
Foxit PDF Reader > Preferences	PDF/A View Mode	Enable this option and specify whether to open documents in PDF/A view mode.  Choose "Never" to never open documents in PDF/A view mode.  Choose "Only for PDF/A documents" to switch to read-only mode automatically when a PDF/A document is opened.  This will change the settings in Preferences > Documents > PDF/A View Mode.
Foxit PDF Reader > Preferences	Program Name	Change the program's name. The default is 'Foxit PDF Reader'.
Foxit PDF Reader > Preferences	Protected View	Enable this option to turn on protected view in order to protect your computers from being harmed by files originated from potentially unsafe locations. This will change the setting in Preferences > Security > Protected

		View.
Foxit PDF Reader > Preferences	Require password to use signatures	Enable this option to require users to set a password for the signature while creating a new signature. This will change the setting of 'Require password to use this signature' in Foxit eSign > Create Signature > Options.
Foxit PDF Reader > Preferences	Remove 'Registration'	Forbid 'Registration' dialog and remove 'Registration' item from 'Help' tab.
Foxit PDF Reader > Preferences	Share the PDF file that caused crash	Enable this option to always share the PDF file that caused crash. This will change the corresponding setting of 'Share the PDF file that caused this crash' option in Crash Report.
Foxit PDF Reader > Preferences	Show Start Page	Change the settings of Start Page.
Foxit PDF Reader > Preferences	Status Bar	Change the settings of Status Bar.
Foxit PDF Reader > Preferences	Trusted Applications	Enable this option and input the name of the trusted application in the list. The listed application will be adding in the Trusted Apps in <b>Preferences</b> > <b>Trust Manager</b> settings.
Foxit PDF Reader > Preferences	Use GDI+ Output for all types of printers	Enable this option to use GDI+ output for PS driver printers (excluding PCL driver printer). This will change the corresponding setting in <b>Preferences</b> > <b>Print</b> .
Foxit PDF Reader > Preferences	User Experience Improvement	Change the settings for anonymous data collection. This will change the corresponding setting in <b>Preferences</b> > <b>General</b> .
Foxit PDF Reader > RMS > Preferences	Add 'protected' to the name of encrypted files	Append "(protected)" to the end of the file name of encrypted files.
Foxit PDF Reader > RMS > Preferences Foxit PDF Reader > RMS > Preferences	AIP default and mandatory labeling Encrypt Metadata	Enable this option to allow users to set up default and mandatory labeling.  Encrypt document metadata. This disables the setting in Professors
RMS > Preferences  Foxit PDF Reader >	Microsoft IRM	disables the setting in 'Preferences > AIP Setting'.  Enable this option to choose Microsoft
RMS > Preferences	Protection	IRM Protection Version for document encryption. If not defined, Microsoft

		IRM Protection Version 2 (PPDF) is
		used.
Foxit PDF Reader >	RMS Interoperability	If you enable this option, all the
RMS > Preferences		encrypted PDFs will conform to
		Microsoft IRM Protection for PDF
		Specification and hence be able to be
		decrypted by other RMS Viewer.
Foxit PDF Reader >	Save As	Turn on the Save As feature for AIP
RMS > Preferences		protected files.
Foxit PDF Reader >	Admin Console server	Set the default Admin Console server.
Admin Console		The end users can use this server URL
		to connect to their enterprise Admin
		Console server.
Foxit PDF Reader >	Update server	Set the path of update server.
Admin Console		

## **Using Foxit Customization Wizard**

Foxit Customization Wizard (hereafter, "the Wizard") is a configuration utility for customizing (configuring) the Foxit PDF Editor or Foxit PDF Reader installer before large scale deployment. For example, you can license the product on a volume scale with the Wizard so that you do not need to register and personalize each copy of the installation. Foxit PDF Editor or Reader will retain all your configuration settings when you upgrade it to a new version.

The Wizard allows enterprise IT administrators to do the following:


- Modify an existing MSI package and save all the modifications into a transform file (mst)
- Directly configure settings from scratch and save all the configurations as an XML (.xml) file.
- Customize settings based on an existing XML (.xml) file.
- Configure which digital ID files are allowed to use.

#### **Get started**

Run the Wizard, you will see the following options on the Welcome page:

- MSI
- XML Editor for Foxit PDF Editor
- XML Editor for Foxit PDF Reader
- SignITMgr

Please select one option to begin. Take **MSI** for example. After you open an MSI installer, you will see the Wizard workspace below.



A. Title Bar

B. Menu Bar

C. The Navigation bar

D. The main work area

The workspace is made up of four parts: Title Bar, the top Menu bar, the Navigation bar, and the main work area.

- 1. The **Title bar** in the top left corner shows the corresponding option you choose on the Welcome page.
- 2. The top **Menu bar** provides key menu options, like "Open", "Save", "Information", and "About".
- 3. The left-hand **Navigation bar** links to the specific configurable options.
- 4. The **Main Work Area** displays configurable options according to the configuration settings you choose.

For more detailed instructions, please click the icon on the top Menu bar and choose **User Guide**, which covers all features included in Foxit Customization Wizard.

# **Contact Us**

Feel free to contact us should you need any information or have any problems with our products. We are always here, ready to serve you better.

#### • Office Address:

Foxit Software Incorporated 39355 California Street Suite 302 Fremont, CA 94538 USA

#### • Sales:

1-866-680-3668

#### • Support & General:

Support Center

1-866-MYFOXIT, 1-866-693-6948

#### • Website:

www.foxit.com

#### • E-mail:

Marketing - marketing@foxit.com